Guides & Tutorials (/docs/)

- » Email Server Guides (/docs/email/)
- » Email Clients (/docs/email/clients/)
- » Install SquirrelMail on Ubuntu 16.04 or Debian 8

Install SquirrelMail on Ubuntu 16.04 or Debian 8

Updated Tuesday, June 14, 2016 by Edward Angert

Use promo code DOC\$10 for \$10 credit on a new account.

Try this Guide

Contribute on GitHub

View Project (https://github.com/linode/docs) | View File (https://github.com/linode/docs/blob/master/docs/email/clients/install-squirrelmail-on-ubuntu-16-04-or-debian-8.md) | Edit File (https://github.com/linode/docs/edit/master/docs/email/clients/install-squirrelmail-on-ubuntu-16-04-or-debian-8.md)

SquirrelMail is a webmail package, written in PHP, which supports both SMTP and IMAP protocols, and features cross-platform compatibility. SquirrelMail requires a web server with PHP to run properly. For this guide we'll be using Apache 2. If you don't already have Apache and PHP installed, you can check our LAMP Server on Ubuntu 16.04 (/docs/websites/lamp/install-lamp-on-ubuntu-16-04) or LAMP Server on Debian 8 (/docs/websites/lamp/lamp-on-debian-8-jessie) guide.

Note

This guide is written for a non-root user. Commands that require elevated privileges are prefixed with sudo. If you're not familiar with the sudo command, you can check our Users and Privileges (/docs/tools-reference/linux-users-and-groups) guide.

Installation

Update the system and install SquirrelMail from the repositories.

1. First, install the most recent system updates:

```
sudo apt-get update
sudo apt-get upgrade
```

2. Install SquirrelMail:

```
1 sudo apt-get install squirrelmail
```

Configure the Virtual Host

To access SquirrelMails's web interface, create and configure a copy of its default virtual host configuration file in the Apache directory. Configure the settings in the copied file to match your Linode and domain settings.

1. SquirrelMail provides a default configuration file for Apache in /etc/squirrelmail/apache.conf . Copy this configuration file into your sites-available folder with the command:

```
sudo cp /etc/squirrelmail/apache.conf /etc/apache2/sites-available/squirrelmail.conf
```

2. Edit the configuration file to uncomment the <virtualHost 1.2.3.4:80> block by removing the pound symbol (#), as shown below. Edit the IP and ServerName to match your Linode and domain settings:

File: /etc/apache2/sites-available/squirrelmail

```
1
    Alias /squirrelmail /usr/share/squirrelmail
2
3
    <Directory /usr/share/squirrelmail>
4
      Options FollowSymLinks
5
       <IfModule mod_php5.c>
6
        php_flag register_globals off
7
      </IfModule>
8
      <IfModule mod_dir.c>
9
        DirectoryIndex index.php
10
       </IfModule>
11
      # access to configtest is limited by default to prevent information leak
12
13
      <Files configtest.php>
14
        order deny,allow
15
        deny from all
16
        allow from 127.0.0.1
17
      </Files>
    </Directory>
18
19
    # users will prefer a simple URL like http://webmail.example.com
20
21
    <VirtualHost *:80>
22
      DocumentRoot /usr/share/squirrelmail
23
      ServerName squirrelmail.example.com
24
    </VirtualHost>
25
26
    # redirect to https when available (thanks omen@descolada.dartmouth.edu)
27
28
    # Note: There are multiple ways to do this, and which one is suitable for
29
    # your site's configuration depends. Consult the apache documentation if
30
    # you're unsure, as this example might not work everywhere.
31
32
    #<IfModule mod_rewrite.c>
33
    # <IfModule mod_ssl.c>
34
         <Location /squirrelmail>
35
           RewriteEngine on
36
    #
           RewriteCond %{HTTPS} !^on$ [NC]
37
           RewriteRule . https://%{HTTP_HOST}%{REQUEST_URI} [L]
38
    # </IfModule>
39
40
    #</IfModule>
```

Note

If Apache is serving other virtual hosts you may need to adjust them and/or this configuration file to prevent any conflicts. If you're running Apache solely for SquirrelMail, you may still want to remove the default virtual host from sites-enabled.

3. Enable the new virtual host:

```
1 sudo a2ensite squirrelmail.conf
```

4. Reload Apache:

```
1 sudo systemctl reload apache2.service
```

You should now be able to see SquirrelMail's default login page in your browser after navigating to your Linode's IP address or domain:




Configure SquirrelMail

Before using SquirrelMail for the first time, configure it to access your mail server. SquirrelMail provides a tool called squirrelmail-configure, an interactive interface which edits the /etc/squirrelmail/config.php file for you with the input you provide.

1. Launch the squirrelmail-configure application:

```
1 sudo squirrelmail-configure
```

This will bring up the menu shown below:



2. There are many options to adjust here; too many for the scope of this guide. The only settings required to make SquirrelMail work are the Server Settings. Enter 2 to bring up the Server Settings submenu:

```
SquirrelMail Configuration: Read: config.php (1.4.0)

Server Settings

General

1. Domain : trim(implode('', file('/etc/'.(file_exists('/etc/mailname')?'mail':'host').'name')))

2. Invert Time : false
3. Sendmail or SMTP : SMTP

A. Update IMAP Settings : localhost:143 (other)

B. Update SMTP Settings : localhost:25

R. Return to Main Menu
C. Turn color on
S. Save data
Q. Quit

Command >> 

I
```

(/docs/assets/1518-squirrelmail-config_2.png)

3. If your mail server is on the same Linode as your SquirrelMail installation, you may not need to make any adjustments to the default settings. Otherwise, adjust the **Domain**, **IMAP**, and **SMTP** settings to match the mail server you want to connect to. You can find additional configuration tips for this section from SquirrelMail's official documentation (http://squirrelmail.org/docs/admin/admin-5.html#ss5.3).

Note

If your email server uses STARTTLS encryption, as our Email with Postfix, Dovecot, and MySQL (/docs/email/postfix/email-with-postfix-dovecot-and-mysql) guide does, You will not be able to authenticate using this version of Squirrelmail. Version 1.5.1 and higher can use STARTTLS, but are in development and not available in the main repositories. You can download (https://squirrelmail.org/download.php) the latest build from Squirrelmail's website.

4. When done, press s to save your changes, then press Q to quit.

Sign In to the Web Interface

1. At this point you should be able to log in to the SquirrelMail Login page using your email credentials. Navigate in your web browser to the Linode's IP address, or domain name depending on how you've configured the virtual host:



(/docs/assets/1520-squirrelmail login filled.png)

2. The interface layout follows standard email convention; all common functions should be easily accessible:



(/docs/assets/1513-squirrelmail inbox.png)

3. Once you're finished, you can sign out using the link in the upper-right corner. Always remember to sign out if you're using a public computer.

More Information

You may wish to consult the following resources for additional information on this topic. While these are provided in the hope that they will be useful, please note that we cannot vouch for the accuracy or timeliness of externally hosted materials.

Official SquirrelMail Documentation (http://squirrelmail.org/documentation/)

This guide is published under a CC BY-ND 4.0 (https://creativecommons.org/licenses/by-nd/4.0) license.

Get paid to write for Linode.

We're always expanding our docs. If you like to help people, can write, and want to earn some cash, learn how you can earn \$250 for every guide you write (/docs/contribute) and we publish.

Get started in the Linode Cloud today.

Create an Account (https://manager.linode.com/session/signup)

Overview (https://www.linode.com/linodes)

Plans & Pricing (https://www.linode.com/pricing)

Features (https://www.linode.com/linodes)

Add-Ons (https://www.linode.com/addons)

Managed (https://www.linode.com/managed)

Professional Services (https://www.linode.com/professional-services)

Resources (https://www.linode.com/docs)

Guides & Tutorials (https://www.linode.com/docs)

Speed Test (https://www.linode.com/speedtest)

Forum (https://forum.linode.com/)

Chat (https://www.linode.com/chat)

System Status (http://status.linode.com/)

Company (https://www.linode.com/about)

About Us (https://www.linode.com/about)

Blog (https://blog.linode.com)

Press (https://www.linode.com/press)

Referral System (https://www.linode.com/referrals)

Careers (https://www.linode.com/careers)

Contact Us (https://www.linode.com/contact)

855-4-LINODE (tel:+18554546633)

(855-454-6633) (tel:+18554546633)

Intl.: +1 609-380-7100 (tel:+16093807100)

Email us (mailto:support@linode.com)

😭 (https://facebook.com/linode) 🖸 (https://twitter.com/linode) 🕲 (https://plus.google.com/+linode/) 🛅 (https://linkedin.com/company/lino

© 2017 Linode, LLC

Terms of Service (https://www.linode.com/tos)

Privacy Policy (https://www.linode.com/privacy)

Security (https://www.linode.com/security)

Standards & Compliance (https://www.linode.com/compliance)